

E36300 series Power Supply

Version 2.1.3-1.0.4-1.14 Information

Released Date:	29 Apr 2024
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bug Fixes

- Fixed instrument reboot after open and close of telnet connection for multiple times

Version 2.1.0-1.0.4-1.12 Information

Released Date:	22 Jan 2020
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bug Fixes

- Added comma for Fetch:dlog command in between channel and voltage/current
- Fixed LAN issues
- Fixed output on after power off with off delay

Version 2.0.8-1.0.4-1.12 Information

Released Date:	3 Apr 2019
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bug Fixes

- To increase LIST repeat count from maximum 256 to 9999.
- To resolve intermittent faulty reboot during calibration.

Version 2.0.6-1.0.3-1.10 Information

Released Date:	16 Jan 2019
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bugs Fixes

- Fixed abnormal behavior of Inhibit latched function.
- Fixed unit hang issue during AC line interruption.

Version 2.0.1-1.0.2-1.06 Information

Released Date:	26 Feb 2018
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bugs Fixes

- Fixed extra current limit for series mode to avoid inaccurate reading and added extra handling for status reading on both CH2 and CH3.

Version 1.1.1-1.0.2-1.05 Information

Released Date:	26 Feb 2018
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Bug Fixes

- Fixed the knob inconsistency issue
- Fixed the store/recall issues
- Fixed the relay state after power cycle (E3631A Persona Mode)
- Fixed incorrect configuration on series mode
- Fixed the unit hung issues

Enhancements

- Added Multiple Languages help (French, German, Japanese, Korean, Chinese, and Russian)
- Enhanced the SCPI datalog fetch command parameter to support up to 65536
- Enhanced the front panel to run LIST when trigger source set to IO

Version 1.0.4-1.0.0-1.04

Released Date:	04 Apr 2017
Requirements category (e.g., operating system):	Microsoft Windows XP, Microsoft Windows 7, Microsoft Windows 8, Microsoft Windows 10

Initial Release

© Keysight Technologies 2023-2024

